
cepton_sdk Documentation

Cepton Technologies

Jul 10, 2019

CONTENTS

1	Overview	1
2	Errors	3
3	Setup	7
4	Sensors	11
5	Points	15
6	Networking	17
7	Capture Replay	19
8	API	21
9	Utilities	23
10	Samples	29
	Index	41

OVERVIEW

The Cepton SDK provides the following features

- **Parsing:** parse sensor packets
- **Calibration:** apply sensor calibration
- **Networking:** listen for sensor packets
- **Capture Replay:** read sensor packets from a PCAP file
- **Frame Accumulation:** accumulate and output sensor points by frame

Currently, the Cepton LiDAR packet formats are under active development, and are not publicly available. The SDK is required for **Parsing** and **Calibration**. All other SDK features are optional, and can be done manually by the user.

For prototyping, it is recommended to start with the high level methods in *API* and *Utilities*.

1.1 Timestamps

All `int64` timestamps are microseconds since the Unix epoch (UTC). Point timestamps are based on one of the following sources (the first valid source is used):

1. GPS (NMEA + PPS)
2. PTP
3. Host PC

All `float` and `int64` time differences are seconds (measurement period, replay time, frame length, etc.).

1.2 Multiple Returns

To enable multiple returns, pass the `CEPTON_SDK_CONTROL_ENABLE_MULTIPLE_RETURNS` flag during initialization.

The returns are as follows:

1. Strongest signal.
2. Furthest signal, if it is not the strongest. Otherwise, the second strongest signal.

1.3 Concurrency

- If networking is enabled, the sdk creates 2 threads for networking. All callbacks occur in these networking threads.
- If networking is disabled, the sdk does not create any threads. All callbacks occur in the main thread.
- All sdk getter functions are thread safe, and can be called from callbacks. Other sdk functions are not guaranteed to be thread safe, and can cause deadlock if called from callbacks.

1.4 Minimal SDK

If desired, the following SDK features can be disabled in the SDK and performed manually by the user:

- Networking: *Network*.
- Capture Replay: *Replay*.
- Frame Accumulation: *Frame*.

ERRORS

2.1 Types

class SensorError : public runtime_error

Error returned by most functions.

Implicitly convertible from/to SensorErrorCode. Getter functions do not return an error, because they cannot fail. Will call CEPTON_RUNTIME_ASSERT if nonzero error is not checked (call ignore to manually use error).

Public Functions

SensorError (*SensorErrorCode* code_, **const** std::string &msg_)

SensorError (*SensorErrorCode* code_)

SensorError ()

~SensorError ()

SensorError (**const** *SensorError* &other)

SensorError &**operator=** (**const** *SensorError* &other)

bool used () **const**
Internal use only.

void ignore () **const**
Mark error as used.

const std::string &**msg** () **const**
Returns error message;.

SensorErrorCode **code** () **const**
Returns error code.

operator SensorErrorCode () **const**
Implicitly convert to SensorErrorCode.

operator bool () **const**
Returns false if code is CEPTON_SUCCESS, true otherwise.

const char ***name** () **const**

bool **is_error** () const

bool **is_fault** () const

_CeptonSensorErrorCode

Values:

0

1

2

4

5

6

Networking error.

7

8

Invalid value or uninitialized struct.

9

10

11

12

13

14

15

1000

Internal parameter out of range.

1001

Reading exceed spec.

1002

Reading exceeds spec.

1003

1004

1005

1006

1007

1008

typedef CeptonSensorErrorCode cepton_sdk::SensorErrorCode

typedef int32_t CeptonSensorErrorCode

2.2 Methods

const char* **cepton_sdk::get_error_code_name** (*SensorErrorCode* error_code)

Returns string name of error code.

Returns empty string if error code is invalid.

bool **cepton_sdk::is_error_code** (*SensorErrorCode* error_code)

Returns true if error name is of the form CEPTON_ERROR_*, false otherwise.

bool **cepton_sdk::is_fault_code** (*SensorErrorCode* error_code)

Returns true if error name is of the form CEPTON_FAULT_*, false otherwise.

SensorError **cepton_sdk::get_error** ()

Returns and clears the last sdk error.

Called automatically by all C++ methods, so only useful when calling C methods directly.

3.1 Types

`_CeptonSDKControl`

SDK control flags.

Values:

- 1
Disable networking operations.
Useful for running multiple instances of sdk in different processes. Must pass packets manually to `cepton_sdk::mock_network_receive`.
- 2
Disable marking image clipped points as invalid.
Does not affect number of points returned.
- 3
Disable marking distance clipped points as invalid.
Does not affect number of points returned.
- 4
Enable multiple returns.
When set, `cepton_sdk::SensorInformation::return_count` will indicate the number of returns per laser. Can only be set at sdk initialization.
- 5
Enable marking stray points as invalid (measurement noise).
Uses `cepton_sdk::util::StrayFilter` to mark points invalid.
Does not affect number of points returned.
- 6
Always use packet timestamps (disable GPS/PTP timestamps).
- 7
Enable marking crosstalk points as invalid.

typedef CeptonSDKControl `cepton_sdk::Control`

typedef uint32_t `CeptonSDKControl`

`_CeptonSDKFrameMode`

Controls frequency of points being reported.

Values:

- 0 Report points by packet.
- 1 Report points at fixed time intervals.
Interval controlled by *CeptonSDKFrameOptions::length*.
- 2 Report points when the field of view is covered once.
 - For HR80 series, detects half scan cycle (left-to-right or right-to-left).
- 3 Report points when the scan pattern goes through a full cycle.
Typically 2x longer frame than COVER mode.
 - For HR80 series, detects full scan cycle (left-to-right-to-left).
 - For VISTA series, internally uses TIMED mode.

```
typedef CeptonSDKFrameMode cepton_sdk::FrameMode
```

```
typedef uint32_t CeptonSDKFrameMode
```

```
struct CeptonSDKFrameOptions
```

Public Members

size_t **signature**

Internal use only.

CeptonSDKFrameMode **mode**

Default: CEPTON_SDK_FRAME_STREAMING.

float **length**

Frame length [seconds].

Default: 0.05. Only used if mode=CEPTON_SDK_FRAME_TIMED.

```
typedef CeptonSDKFrameOptions cepton_sdk::FrameOptions
```

```
FrameOptions cepton_sdk::create_frame_options ()
```

Create default frame options.

```
struct CeptonSDKOptions
```

SDK initialization options.

Public Members

size_t **signature**

Internal use only.

CeptonSDKControl **control_flags**

Default: 0.

struct *CeptonSDKFrameOptions* **frame**

uint16_t port
Default: 8808.

typedef CeptonSDKOptions cepton_sdk::Options

Options cepton_sdk::create_options()
Create default options.

typedef void (*cepton_sdk::FpSensorErrorCallback) (*SensorHandle* handle, *SensorErrorCode* error_code, **const** char *error_msg, **const** void *error_data, size_t error_data_size, void *user_data)

Callback for receiving sdk and sensor errors.

Currently, error_data is not used.

3.2 Methods

SensorError cepton_sdk::initialize (int version, **const** *Options* &options = create_options(), **const** *FpSensorErrorCallback* &cb = nullptr, void ***const** user_data = nullptr)

Initializes settings and networking.

Must be called before any other sdk function listed below.

SensorError cepton_sdk::deinitialize()
Resets everything and deallocates memory.

SensorError cepton_sdk::set_control_flags (*Control* mask, *Control* flags)

Control cepton_sdk::get_control_flags()

bool cepton_sdk::has_control_flag (*Control* flag)

uint16_t cepton_sdk::get_port()

SensorError cepton_sdk::set_port (uint16_t port)
Sets network listen port.

Default: 8808.

SensorError cepton_sdk::set_frame_options (**const** CeptonSDKFrameOptions &options)

FrameMode cepton_sdk::get_frame_mode()

float cepton_sdk::get_frame_length()

SENSORS

4.1 Types

```
typedef CeptonSensorHandle cepton_sdk::SensorHandle  
    Sensor identifier.
```

```
_CeptonSensorModel
```

Values:

1

2

3

4

5

6

7

8

9

10

11

12

12

```
typedef CeptonSensorModel cepton_sdk::SensorModel
```

```
typedef CeptonSensorInformation cepton_sdk::SensorInformation
```

```
struct CeptonSensorInformation
```

Public Members

CeptonSensorHandle **handle**

uint64_t **serial_number**

char CeptonSensorInformation::model_name[28]

CeptonSensorModel **model**

```
uint16_t reserved
char CeptonSensorInformation::firmware_version[28]
uint8_t major
uint8_t minor
uint8_t CeptonSensorInformation::unused[2]
struct CeptonSensorInformation::@16 formal_firmware_version
float last_reported_temperature
    [celsius]
float last_reported_humidity
    [%]
float last_reported_age
    [hours]
float measurement_period
    Time between measurements [seconds].
int64_t ptp_ts
    [microseconds]
uint8_t gps_ts_year
    0-99 (2017 -> 17)
uint8_t gps_ts_month
    1-12
uint8_t gps_ts_day
    1-31
uint8_t gps_ts_hour
    0-23
uint8_t gps_ts_min
    0-59
uint8_t gps_ts_sec
    0-59
uint8_t return_count
uint8_t segment_count
    Number of image segments.
uint32_t flags
uint32_t is_mocked
    Created by capture replay.
uint32_t is_pps_connected
    GPS PPS is available.
uint32_t is_nmea_connected
    GPS NMEA is available.
uint32_t is_ptp_connected
    PTP is available.
uint32_t is_calibrated
```


`uint32_t is_over_heated`

Hit temperature limit (only available in Vista Gen2 for now)

`uint32_t is_sync_firing_enabled`

union *CeptonSensorInformation*::@17 *CeptonSensorInformation*::@18

4.2 Methods

`std::size_t cepton_sdk::get_n_sensors()`

Get number of sensors attached. Use to check for new sensors. Sensors are not deleted until deinitialization.

SensorError `cepton_sdk::get_sensor_handle_by_serial_number`(`uint64_t serial_number`,
SensorHandle &handle)

Returns error if sensor not found.

SensorError `cepton_sdk::get_sensor_information_by_index`(`std::size_t idx`, *SensorInformation* &info)

Valid indices are in range [0, n_sensors). Returns error if index invalid.

SensorError `cepton_sdk::get_sensor_information`(*SensorHandle* handle, *SensorInformation* &info)

Returns error if sensor not found.

5.1 Types

```
typedef CeptonSensorImagePoint cepton_sdk::SensorImagePoint
```

```
struct CeptonSensorImagePoint
```

Point in image coordinates (focal length = 1).

To convert to 3d point, refer to `ception_sdk_util.hpp`.

Public Members

```
int64_t timestamp
```

Unix time [microseconds].

```
float image_x
```

x image coordinate.

```
float distance
```

Distance [meters].

```
float image_z
```

z image coordinate.

```
float intensity
```

Diffuse reflectance.

```
CeptonSensorReturnType return_type
```

```
uint8_t flags
```

```
uint8_t valid
```

```
uint8_t saturated
```

```
union CeptonSensorImagePoint::@21 CeptonSensorImagePoint::@22
```

```
uint8_t CeptonSensorImagePoint::reserved[2]
```

5.2 Methods

```
typedef void (* FpCeptonSensorImageDataCallback) (CeptonSensorHandle handle,  
size_t n_points, const struct Cep-  
tonSensorImagePoint *c_points,  
void *user_data)
```

SensorError cepton_sdk::**listen_image_frames** (FpSensorImageDataCallback *cb*, void ***const** *user_data*)

Sets image frames callback.

Returns points at frequency specified by *cepton_sdk::FrameOptions::mode*. Each frame contains all possible points (use *cepton_sdk::SensorImagePoint::valid* to filter points). Points are ordered by measurement, segment, and return:

```
measurement_count = n_points / (segment_count * return_count)
idx = ((i_measurement) * segment_count + i_segment) * return_count + i_return
```

Returns error if callback already registered.

SensorError cepton_sdk::**unlisten_image_frames** ()

NETWORKING

6.1 Types

```
typedef void (*cepton_sdk::FpNetworkReceiveCallback) (SensorHandle handle, int64_t  
timestamp, uint8_t const  
*buffer, size_t buffer_size, void  
*user_data)
```

Callback for receiving network packets.

Parameters

- `handle`: Unique sensor identifier (e.g. IP address). Returns error if callback already set.

6.2 Methods

```
SensorError cepton_sdk::listen_network_packets (FpNetworkReceiveCallback cb, void  
*const user_data)
```

Sets network packets callback.

Only 1 callback can be registered.

```
SensorError cepton_sdk::unlisten_network_packets ()
```

```
SensorError cepton_sdk::clear ()
```

Clears sensors.

Use when loading/unloading capture file.

CAPTURE REPLAY

PCAP capture file replay. Source code can be found in the *source* folder. Functions are not thread safe, and should only be called from the main thread.

`bool cepton_sdk::capture_replay::is_open()`

SensorError `ception_sdk::capture_replay::open(const std::string &path)`
Opens capture file.

Must be called before any other replay functions listed below.

SensorError `ception_sdk::capture_replay::close()`

`const char *ception_sdk::capture_replay::get_filename()`

`uint64_t cepton_sdk::capture_replay::get_start_time()`
Returns capture start timestamp (unix time [microseconds]).

`float cepton_sdk::capture_replay::get_position()`
Returns capture file position [seconds].

`float cepton_sdk::capture_replay::get_length()`
Returns capture file length [seconds].

`bool cepton_sdk::capture_replay::is_end()`
Returns true if at end of capture file.

This is only relevant when using `resume_blocking` methods.

SensorError `ception_sdk::capture_replay::seek(float position)`
Seek to capture file position [seconds].

Position must be in range [0.0, capture length). Returns error if position is invalid.

SensorError `ception_sdk::capture_replay::set_enable_loop(bool value)`
If enabled, replay will automatically rewind at end.

`bool cepton_sdk::capture_replay::get_enable_loop()`

SensorError `ception_sdk::capture_replay::set_speed(float speed)`
Replay speed multiplier for asynchronous replay.

`float cepton_sdk::capture_replay::get_speed()`

SensorError `ception_sdk::capture_replay::resume_blocking_once()`
Replay next packet in current thread without sleeping.

Pauses replay thread if it is running.

SensorError `ception_sdk::capture_replay::resume_blocking(float duration)`
Replay multiple packets synchronously.

No sleep between packets. Resume duration must be non-negative. Pauses replay thread if it is running.

`bool cepton_sdk::capture_replay::is_running()`

Returns true if replay thread is running.

SensorError `cepton_sdk::capture_replay::resume()`

Packets are replayed in realtime. Replay thread sleeps in between packets.

SensorError `cepton_sdk::capture_replay::pause()`

Pauses asynchronous replay thread.

High level SDK api for prototyping (*cepton_sdk_api.hpp*). Methods are agnostic to live/replay mode.

`bool cepton_sdk::api::is_live()`
Returns true if capture replay is not open.

`bool cepton_sdk::api::is_end()`

`int64_t cepton_sdk::api::get_time()`
Returns capture replay time or live time.

`SensorError cepton_sdk::api::wait` (float *t_length* = -1.0f)
Sleeps or resumes capture replay for duration.
If *t_length* < 0, then waits forever.

8.1 Errors

`const SensorError &cepton_sdk::api::check_error` (const *SensorError* &*error*, const std::string &*msg* = "")

Handles error.

If error, raises exception. Otherwise, prints error.

`const SensorError &cepton_sdk::api::log_error` (const *SensorError* &*error*, const std::string &*msg* = "")

Prints error.

`void cepton_sdk::api::default_on_error` (*SensorHandle* *h*, *SensorErrorCode* *error_code*, const char *const *error_msg*, const void *const *error_data*, std::size_t *error_data_size*, void *const *instance*)

Basic SDK error callback.

Calls `cepton_sdk::api::check_error_code`.

8.2 Setup

`SensorError cepton_sdk::api::initialize` (*Options* *options* = *create_options*(), const std::string &*capture_path* = "")

Initialize SDK and optionally starts capture replay.

`class SensorErrorCallback : public cepton_sdk::util::Callback<SensorHandle, const SensorError&>`
Callback for sensor errors.

Public Static Functions

```
static void global_on_callback(SensorHandle handle, SensorErrorCode error_code, const
                             char *error_msg, const void *const error_data, size_t er-
                             ror_data_size, void *const instance)
```

```
class SensorImageFrameCallback : public cepton_sdk::util::Callback<SensorHandle, std::size_t, const SensorImagePos
    Callback for image frames.
    Must call initialize before use.
```

Public Functions

```
~SensorImageFrameCallback()
```

```
SensorError initialize()
```

```
SensorError deinitialize()
```

```
bool is_initialized() const
```

```
class NetworkPacketCallback : public cepton_sdk::util::Callback<SensorHandle, int64_t, uint8_t const *, std::size_t>
    Callback for network packets.
    Must call initialize before use.
```

Public Functions

```
~NetworkPacketCallback()
```

```
SensorError initialize()
```

```
SensorError deinitialize()
```

8.3 Sensors

```
bool cepton_sdk::api::has_sensor_by_serial_number(uint64_t serial_number)
```

```
SensorError cepton_sdk::api::get_sensor_information_by_serial_number(uint64_t se-
                                                                    rial_number,
                                                                    SensorIn-
                                                                    formation
                                                                    &info)
```

Returns error if sensor not found.

```
std::vector<uint64_t> cepton_sdk::api::get_sensor_serial_numbers()
    Returns serial numbers for all sensors.
```

UTILITIES

Utility functions and classes for prototyping (*cepton_sdk_util.hpp*).

9.1 Common

`int64_t cepton_sdk::util::get_timestamp_usec()`

Returns current unix timestamp [microseconds].

This is the timestamp format used by all sdk functions.

9.2 Points

`void cepton_sdk::util::convert_image_point_to_point` (float *image_x*, float *image_z*, float *distance*, float &*x*, float &*y*, float &*z*)

Convert image point to 3d point.

struct SensorPoint

3d point class.

Can't subclass from SensorImagePoint, needs to be POD.

Public Members

`int64_t timestamp`

Unix time [microseconds].

`float image_x`

x image coordinate.

`float distance`

Distance [meters].

`float image_z`

z image coordinate.

`float intensity`

Diffuse reflectance.

`CeptonSensorReturnType return_type`

`uint8_t flags`

```

uint8_t valid
uint8_t saturated
union cepton_sdk::util::SensorPoint::[anonymous] [anonymous]
uint8_t reserved[5]
float x
    x cartesian coordinate
float y
    y cartesian coordinate
float z
    z cartesian coordinate
void cepton_sdk::util::convert_sensor_image_point_to_point (const SensorImage-
Point &image_point,
SensorPoint &point)
Convenience method to convert ception_sdk::SensorImagePoint to
ception_sdk::SensorPoint.

```

9.3 Transforms

class CompiledTransform

3d translation and rotation.

For more functionality, use Eigen's Geometry module.

Public Functions

void **apply** (float &x, float &y, float &z)
 Apply transformation to 3d position.

Public Static Functions

static *CompiledTransform* **create** (const float *const translation, const float *const rota-
 tion)
 Create from translation and rotation.

Parameters

- translation: Cartesian (x, y, z)
- rotation: Quaternion (x, y, z, w)

9.4 Callbacks

template<typename ...TArgs>

class Callback

Expands SDK callback functionality.

Allows for multiple callbacks to be registered. Allows for registering lambdas and member functions. See `samples/basic.cpp`.

Public Functions

void **clear** ()

Clear all listeners.

SensorError **listen** (const std::function<void> TArgs...
> &func, uint64_t *const id = nullptr) Register std::function.

template<typename TClass>

SensorError **listen** (TClass *const instance, MemberFunction<TClass, TArgs...> func, uint64_t
*const id = nullptr)
Register instance member function.

void **emit** (TArgs... args) const
Emit callback.

void **operator** () (TArgs... args) const
Emit callback.

Public Static Functions

static void **global_on_callback** (TArgs... args, void *const instance)
Used for registering as c callback.

9.5 Frames

class FrameDetector

Detects frames in streaming sensor data.

Public Functions

FrameDetector (const *SensorInformation* &sensor_info)

const *FrameOptions* &**get_options** () const

SensorError **set_options** (const *FrameOptions* &options)

void **reset** ()
Completely resets detector.

Only use if also clearing points accumulator.

bool **add_point** (const *SensorImagePoint* &point)
Returns true if frame found.

Automatically resets after frame is found.

Public Members

bool **frame_found**

int **frame_idx**

float **frame_x**
Number of points in current frame.

class FrameAccumulator
Accumulates image points, and emits frames to callback.
See `samples/frame.cpp`.

Public Functions

FrameAccumulator (const *SensorInformation* &*sensor_info*)
FrameOptions **get_options** () const
SensorError **set_options** (const *FrameOptions* &*options*)
void **clear** ()
void **add_points** (int *n_points*, const *SensorImagePoint* *const *image_points*)

Public Members

Callback<int, const *SensorImagePoint* *> **callback**

9.6 Organizer

struct OrganizedCloud
The *OrganizedCloud* struct An organized version of the cepton point cloud.

Public Functions

int **getIndex** (int *row*, int *col*, int *n_return*)
getIndex Returns the index of the point corresponding to the inputted row, col and return number.

Return

Parameters

- [in] *row*: Row index
- [in] *col*: Col index
- [in] *n_return*: Return index

Public Members

int64_t **timestamp_start**
timestamp_start The time of the oldest point in the cloud
int64_t **timestamp_end**
timestamp_end The time of the newest point in the cloud
int **height**
height Height of the cloud. Represents how many rows there are in the cloud

int width
width Width of the cloud. Represents how many columns there are in the cloud

int n_returns
n_returns Number of return represented by the cloud.

std::vector<CellInfo> info_cells
info_cells Vector of cell info which provide information about the matching points

std::vector<CeptonSensorImagePoint> points
points Vector of organized points. Stored in Return, Row, Col order. So to get a point at row 10, col 15, return 1 would be points[(row * width

- col) n_returns + return

struct CellInfo
The *CellInfo* struct.

Public Members

bool occupied_cell = false
occupied_cell Is the cell at this index occupied with a point. If false can't assume this represents free space.

int original_index = -1
original_index Index of the point that was used to generate the organized point. Can be used to match back with original data if required. Should only be use if occupied_cell is true.

class Organizer

The *Organizer* class Performs organization on cepton unorganized points. Creates an angular grid, places each point within that grid and outputs a point for each location in the grid in a row/col format. Thread safe. Defaults to a 0.4deg spaced grid.

Public Types

enum OrganizerMode

Values:

RECENT

Output the most recent point from the frame that fell within the grid

CENTER

Output the center of the grid. Uses median point distance.

Public Functions

Organizer (cepton_sdk::SensorInformation sensor_info)
Organizer.

Parameters

- sensor_info: Sensor info for organizer. Used to set min/max angles

```
void organize_points (const int num_points_in, const int n_returns, const CeptonSensorImagePoint *const unorganized_points, cepton_sdk::util::OrganizedCloud &organized_points)  
organize_points
```

Parameters

- [in] *num_points_in*: Number of unorganized points
- [in] *n_returns*: Number of returns
- [in] *unorganized_points*: Unorganized points to process
- [out] *organized_points*: Points in organized form

```
void mode (OrganizerMode mode)  
mode
```

Parameters

- *mode*: Change the mode of the organizer. [RECENT] Points are the most recent which fill within the grid. [CENTER] Points outputted are at the center of the grid. More even spacing but less accurate.

```
void binSize (float bin_size)  
binSize Change the bin size of the organizer
```

Parameters

- *bin_size*: The horizontal and vertical bin size to set. In radians

```
void settings (OrganizerSettings organizer_settings)  
settings
```

Parameters

- *organizer_settings*: Change organizer settings

```
Organizer::OrganizerSettings settings ()  
settings
```

Return The settings the organizer is using

```
struct OrganizerSettings
```

Public Members

```
float horizontal_range_radians = to_radians(70.f)  
float vertical_range_radians = to_radians(30.f)  
float horizontal_bin_size_radians = to_radians(0.4f)  
float vertical_bin_size_radians = to_radians(0.4f)  
OrganizerMode mode = OrganizerMode::RECENT
```


10.1 Basic

Listing 1: samples/basic.cpp

```
1  /**
2   * Sample code for general sdk usage.
3   */
4  #include <iostream>
5  #include <string>
6  #include <vector>
7
8  #include <cepton_sdk_api.hpp>
9
10 class FramesListener {
11 public:
12     void on_image_frame(cepton_sdk::SensorHandle handle, std::size_t n_points,
13                        const cepton_sdk::SensorImagePoint *c_image_points) {
14         // Get sensor info
15         cepton_sdk::SensorInformation sensor_info;
16         cepton_sdk::api::check_error(
17             cepton_sdk::get_sensor_information(handle, sensor_info));
18
19         // Print info
20         if (i_frame < 5) {
21             std::printf("Received %i points from sensor %i\n", (int)n_points,
22                         (int)sensor_info.serial_number);
23         }
24         ++i_frame;
25     }
26
27 private:
28     std::size_t i_frame = 0;
29 };
30
31 int main(int argc, char **argv) {
32     std::string capture_path;
33     if (argc >= 2) capture_path = argv[1];
34
35     // Initialize
36     auto options = cepton_sdk::create_options();
37     cepton_sdk::api::check_error(
38         cepton_sdk::api::initialize(options, capture_path));
39 }
```

(continues on next page)

(continued from previous page)

```

39
40 // Get sensor
41 std::printf("Waiting for sensor to connect...\n");
42 while (cepton_sdk::get_n_sensors() == 0)
43     cepton_sdk::api::check_error(cepton_sdk::api::wait(0.1f));
44 cepton_sdk::SensorInformation sensor_info;
45 cepton_sdk::api::check_error(
46     cepton_sdk::get_sensor_information_by_index(0, sensor_info));
47 std::printf("Sensor: %d\n", (int)sensor_info.serial_number);
48
49 // Listen for frames
50 std::printf("Listening for frames...\n");
51 cepton_sdk::api::SensorImageFrameCallback callback;
52 cepton_sdk::api::check_error(callback.initialize());
53 FramesListener frames_listener;
54 callback.listen(&frames_listener, &FramesListener::on_image_frame);
55
56 // Run
57 cepton_sdk::api::check_error(cepton_sdk::api::wait());
58
59 // Deinitialize
60 cepton_sdk::api::check_error(cepton_sdk::deinitialize());
61 }

```

10.2 C Basic

Listing 2: samples/c_basic.c

```

1  /**
2   * Sample code for general C sdk usage.
3   */
4  #include <stdio.h>
5  #include <time.h>
6
7  #include <cepton_sdk.h>
8
9  int frames_got = 0;
10 time_t first_frame_time = 0;
11 time_t current_frame_time = 0;
12
13 void image_frame_callback(CeptonSensorHandle handle, size_t n_points,
14                          const struct CeptonSensorImagePoint *c_points,
15                          void *user_data) {
16     time_t t = time(NULL);
17
18     if (frames_got == 0) first_frame_time = t;
19     frames_got++;
20     if (frames_got < 50)
21         printf("Frame: %4d Time: %lld\n", frames_got, (long long)t);
22     else
23         printf("Frame: %4d Time: %lld Frame rate: %.1fHz\n", frames_got,
24             (long long)t, frames_got * 1.0 / (t - first_frame_time));
25 }
26

```

(continues on next page)

(continued from previous page)

```

27 int main() {
28     printf("Start\n");
29     fflush(stdout);
30     struct CeptonSDKOptions options = cepton_sdk_create_options();
31     options.frame.mode = CEPTON_SDK_FRAME_TIMED;
32     options.frame.length = 0.1f;
33     CeptonSensorErrorCode ret;
34     ret = cepton_sdk_initialize(CEPTON_SDK_VERSION, &options, NULL, NULL);
35     if (ret != CEPTON_SUCCESS) printf("%s\n", cepton_get_error_code_name(ret));
36     ret = cepton_sdk_listen_image_frames(image_frame_callback, NULL);
37     if (ret != CEPTON_SUCCESS) printf("%s\n", cepton_get_error_code_name(ret));
38
39     while (frames_got < 100)
40         ; // Just spin loop for lack of cross platform sleep in C
41
42     cepton_sdk_deinitialize();
43
44     return 0;
45 }

```

10.3 Callback

Listing 3: samples/callback.cpp

```

1  /**
2   * Sample code for callback usage.
3   */
4  #include <cepton_sdk_api.hpp>
5
6  // Sample global callback.
7  void on_image_frame(cepton_sdk::SensorHandle handle, std::size_t n_points,
8                     const cepton_sdk::SensorImagePoint *c_image_points) {}
9
10 // Sample member callback.
11 class FramesListener {
12 public:
13     void on_image_frame(cepton_sdk::SensorHandle handle, std::size_t n_points,
14                       const cepton_sdk::SensorImagePoint *c_image_points) {}
15 };
16
17 int main(int argc, char **argv) {
18     // Initialize
19     cepton_sdk::api::check_error(cepton_sdk::api::initialize());
20     cepton_sdk::api::SensorImageFrameCallback callback;
21     cepton_sdk::api::check_error(callback.initialize());
22
23     // Listen lambda
24     callback.listen([](cepton_sdk::SensorHandle handle, std::size_t n_points,
25                      const cepton_sdk::SensorImagePoint *c_image_points) {});
26
27     // Listen global function
28     callback.listen(on_image_frame);
29
30     // Listen member function

```

(continues on next page)

(continued from previous page)

```

31 FramesListener frames_listener;
32 callback.listen(&frames_listener, &FramesListener::on_image_frame);
33 }

```

10.4 Error

Listing 4: samples/error.cpp

```

1  /**
2   * Sample code for error callback usage.
3   */
4  #include <cepton_sdk_api.hpp>
5
6  int main(int argc, char** argv) {
7      // Initialize
8      cepton_sdk::api::SensorErrorCallback error_callback;
9      error_callback.listen(
10         [&](cepton_sdk::SensorHandle handle,
11             const cepton_sdk::SensorError& error) { throw error; });
12     cepton_sdk::api::check_error(cepton_sdk::initialize(
13         CEPTON_SDK_VERSION, cepton_sdk::create_options(),
14         error_callback.global_on_callback, &error_callback));
15 }

```

10.5 Sensor

Listing 5: samples/sensor.cpp

```

1  /**
2   * Sample code for sensor information.
3   */
4  #include <string>
5
6  #include <cepton_sdk_api.hpp>
7
8  int main(int argc, char **argv) {
9      std::string capture_path;
10     if (argc >= 2) capture_path = argv[1];
11
12     // Initialize
13     auto options = cepton_sdk::create_options();
14     cepton_sdk::api::check_error(
15         cepton_sdk::api::initialize(options, capture_path));
16     cepton_sdk::api::check_error(cepton_sdk::api::wait(5.0f));
17
18     // Get all sensors
19     const int n_sensors = (int)cepton_sdk::get_n_sensors();
20     for (int i = 0; i < n_sensors; ++i) {
21         cepton_sdk::SensorInformation sensor_info;
22         cepton_sdk::api::check_error(
23             cepton_sdk::get_sensor_information_by_index(i, sensor_info));

```

(continues on next page)

(continued from previous page)

```

24     std::printf("%i: %s\n", (int)sensor_info.serial_number,
25                     sensor_info.model_name);
26 }
27 }

```

10.6 Advanced

10.6.1 Frame

Listing 6: samples/advanced/frame.cpp

```

1  /**
2   * Sample code for custom frame accumulation.
3   */
4  #include <cepton_sdk_api.hpp>
5
6  int main(int argc, char **argv) {
7      std::string capture_path;
8      if (argc >= 2) capture_path = argv[1];
9
10     // Initialize
11     auto options = cepton_sdk::create_options();
12     cepton_sdk::api::check_error(
13         cepton_sdk::api::initialize(options, capture_path));
14     cepton_sdk::api::SensorImageFrameCallback callback;
15     cepton_sdk::api::check_error(callback.initialize());
16
17     // Get sensor
18     while (cepton_sdk::get_n_sensors() == 0)
19         cepton_sdk::api::check_error(cepton_sdk::api::wait(0.1f));
20     cepton_sdk::SensorInformation sensor_info;
21     cepton_sdk::api::check_error(
22         cepton_sdk::get_sensor_information_by_index(0, sensor_info));
23
24     // Create accumulator
25     auto frame_options = cepton_sdk::create_frame_options();
26     frame_options.mode = CEPTON_SDK_FRAME_TIMED;
27     frame_options.length = 0.1f;
28     cepton_sdk::util::FrameAccumulator accumulator(sensor_info);
29     cepton_sdk::api::check_error(accumulator.set_options(frame_options));
30     callback.listen(
31         [&](cepton_sdk::SensorHandle handle, std::size_t n_points,
32             const cepton_sdk::SensorImagePoint *const c_image_points) {
33             if (handle != sensor_info.handle) return;
34             accumulator.add_points((int)n_points, c_image_points);
35         });
36
37     // Listen
38     accumulator.callback.listen(
39         [&](int n_points,
40             const cepton_sdk::SensorImagePoint *const c_image_points) {
41             std::printf("Received %i points\n", n_points);
42         });

```

(continues on next page)

(continued from previous page)

```

43
44     cepton_sdk::api::check_error(cepton_sdk::api::wait(5.0f));
45 }

```

10.6.2 Network

Listing 7: samples/advanced/network.cpp

```

1  /**
2   * Sample code for custom networking.
3   */
4  #include <asio.hpp>
5
6  #include <cepton_sdk_api.hpp>
7
8  using asio::ip::udp;
9
10 class SocketListener {
11 public:
12     SocketListener() : m_socket(m_io_service, udp::v4()) {
13         m_socket.set_option(asio::socket_base::reuse_address(true));
14         m_socket.bind(udp::endpoint(udp::v4(), 8808));
15     }
16
17     void run() {
18         listen();
19         m_io_service.run_for(std::chrono::seconds(5));
20     }
21
22     void listen() {
23         m_socket.async_receive_from(
24             asio::buffer(m_buffer), m_end_point,
25             [this](const asio::error_code& error, std::size_t buffer_size) {
26                 if (buffer_size == 0) return;
27                 if (error == asio::error::operation_aborted) return;
28                 const CeptonSensorHandle handle =
29                     m_end_point.address().to_v4().to_ulong();
30                 // For more accurate timestamps, a separate network receive thread
31                 // should be
32                 // used.
33                 const int64_t timestamp = cepton_sdk::util::get_timestamp_usec();
34                 cepton_sdk::api::check_error(cepton_sdk::mock_network_receive(
35                     handle, timestamp, m_buffer.data(), buffer_size));
36                 listen();
37             });
38     }
39
40 private:
41     asio::io_context m_io_service;
42     udp::socket m_socket;
43     udp::endpoint m_end_point;
44     std::array<uint8_t, 4096> m_buffer;
45 };
46
47 int main() {

```

(continues on next page)

(continued from previous page)

```

48 // Initialize sdk
49 auto options = cepton_sdk::create_options();
50 options.control_flags |= CEPTON_SDK_CONTROL_DISABLE_NETWORK;
51 options.frame.mode = CEPTON_SDK_FRAME_COVER;
52 cepton_sdk::api::check_error(cepton_sdk::api::initialize(options));
53
54 // Listen for points
55 cepton_sdk::api::SensorImageFrameCallback callback;
56 cepton_sdk::api::check_error(callback.initialize());
57 callback.listen([](cepton_sdk::SensorHandle handle, std::size_t n_points,
58                 const cepton_sdk::SensorImagePoint* c_image_points) {
59     std::printf("Received %i points from sensor %lli\n", (int)n_points,
60                (long long)handle);
61 });
62
63 SocketListener listener;
64 listener.run();
65 }

```

10.6.3 Process Multi

Listing 8: samples/advanced/process_multi.cpp

```

1 /**
2  * Sample code for processing multiple sensor data.
3  */
4 #include <string>
5 #include <vector>
6
7 #include <cepton_sdk_api.hpp>
8
9 struct Frame {
10     int64_t timestamp;
11     std::map<cepton_sdk::SensorHandle, std::vector<cepton_sdk::SensorImagePoint>>
12         image_points_dict;
13 };
14
15 class FrameAccumulator {
16 public:
17     void on_image_frame(
18         cepton_sdk::SensorHandle handle, std::size_t n_points,
19         const cepton_sdk::SensorImagePoint* const c_image_points) {
20         cepton_sdk::util::LockGuard lock(m_mutex);
21
22         auto& image_points = m_image_points_dict[handle];
23         image_points.reserve(image_points.size() + n_points);
24         image_points.insert(image_points.end(), c_image_points,
25                             c_image_points + n_points);
26
27         check_and_publish();
28     }
29
30 private:
31     void check_and_publish() {
32         const auto timestamp = cepton_sdk::api::get_time();

```

(continues on next page)

(continued from previous page)

```

33     if (timestamp < m_timestamp) return;
34     if ((timestamp - m_timestamp) < int64_t(m_frame_length * 1e6f)) return;
35     m_timestamp = timestamp;
36
37
38     auto frame = std::make_shared<Frame>();
39     frame->timestamp = timestamp;
40     frame->image_points_dict = m_image_points_dict;
41     m_image_points_dict.clear();
42     queue.push(frame);
43 }
44
45 public:
46     cepton_sdk::util::SingleConsumerQueue<Frame> queue;
47
48 private:
49     std::timed_mutex m_mutex;
50     float m_frame_length = 0.1f;
51     int64_t m_timestamp = 0;
52     std::map<cepton_sdk::SensorHandle, std::vector<cepton_sdk::SensorImagePoint>>
53         m_image_points_dict;
54 };
55
56 int main(int argc, char** argv) {
57     std::string capture_path;
58     if (argc >= 2) capture_path = argv[1];
59
60     auto options = cepton_sdk::create_options();
61     cepton_sdk::api::check_error(
62         cepton_sdk::api::initialize(options, capture_path));
63     cepton_sdk::api::SensorImageFrameCallback callback;
64     cepton_sdk::api::check_error(callback.initialize());
65     if (cepton_sdk::capture_replay::is_open())
66         cepton_sdk::api::check_error(cepton_sdk::capture_replay::resume());
67
68     FrameAccumulator accumulator;
69     callback.listen(&accumulator, &FrameAccumulator::on_image_frame);
70
71     while (true) {
72         const auto frame = accumulator.queue.pop(0.01f);
73         if (!frame) continue;
74         // Do processing
75     }
76 }

```

10.6.4 Process Single

Listing 9: samples/advanced/process_single.cpp

```

1  /**
2   * Sample code for processing single sensor data.
3   */
4  #include <memory>
5  #include <vector>
6

```

(continues on next page)

(continued from previous page)

```

7  #include <cepton_sdk_api.hpp>
8
9  struct Frame {
10     int64_t timestamp;
11     cepton_sdk::SensorHandle handle;
12     std::vector<cepton_sdk::SensorImagePoint> image_points;
13 };
14
15 int main(int argc, char **argv) {
16     std::string capture_path;
17     if (argc >= 2) capture_path = argv[1];
18
19     auto options = cepton_sdk::create_options();
20     cepton_sdk::api::check_error(
21         cepton_sdk::api::initialize(options, capture_path));
22     cepton_sdk::api::SensorImageFrameCallback callback;
23     cepton_sdk::api::check_error(callback.initialize());
24     if (cepton_sdk::capture_replay::is_open())
25         cepton_sdk::api::check_error(cepton_sdk::capture_replay::resume());
26
27     cepton_sdk::util::SingleConsumerQueue<Frame> queue;
28     callback.listen([&](cepton_sdk::SensorHandle handle, std::size_t n_points,
29         const cepton_sdk::SensorImagePoint *c_image_points) {
30         auto frame = std::make_shared<Frame>();
31         frame->timestamp = cepton_sdk::api::get_time();
32         frame->handle = handle;
33         frame->image_points.reserve(n_points);
34         frame->image_points.insert(frame->image_points.end(), c_image_points,
35             c_image_points + n_points);
36         queue.push(frame);
37     });
38
39     while (true) {
40         const auto frame = queue.pop(0.01f);
41         if (!frame) continue;
42         // Do processing
43     }
44 }

```

10.6.5 Replay

Listing 10: samples/advanced/replay.cpp

```

1  /**
2   * Sample code for custom packet replaying.
3   */
4  #include <cepton_sdk/capture.hpp>
5  #include <cepton_sdk_api.hpp>
6
7  class CaptureReplay {
8  public:
9     CaptureReplay(const std::string& path) {
10         cepton_sdk::api::check_error(m_capture.open_for_read(path));
11
12         cepton_sdk::api::check_error(

```

(continues on next page)

(continued from previous page)

```

13         cepton_sdk_set_control_flags(CEPTON_SDK_CONTROL_DISABLE_NETWORK,
14                                     CEPTON_SDK_CONTROL_DISABLE_NETWORK));
15     cepton_sdk::api::check_error(cepton_sdk_clear());
16 }
17
18 ~CaptureReplay() {
19     m_capture.close();
20     if (cepton_sdk_is_initialized()) {
21         cepton_sdk::api::check_error(cepton_sdk_clear());
22     }
23 }
24
25 void run() {
26     while (true) {
27         cepton_sdk::Capture::PacketHeader header;
28         const uint8_t* data;
29         cepton_sdk::api::check_error(m_capture.next_packet(header, data));
30
31         const cepton_sdk::SensorHandle handle =
32             (cepton_sdk::SensorHandle)header.ip_v4 |
33             CEPTON_SENSOR_HANDLE_FLAG MOCK;
34         cepton_sdk::api::check_error(cepton_sdk_mock_network_receive(
35             handle, header.timestamp, data, header.data_size));
36     }
37 }
38
39 private:
40     cepton_sdk::Capture m_capture;
41 };
42
43 int main(int argc, char** argv) {
44     if (argc < 2) return -1;
45     const std::string capture_path = argv[1];
46
47     // Initialize sdk
48     auto options = cepton_sdk::create_options();
49     options.control_flags |= CEPTON_SDK_CONTROL_DISABLE_NETWORK;
50     options.frame.mode = CEPTON_SDK_FRAME_COVER;
51     cepton_sdk::api::check_error(cepton_sdk::api::initialize(options));
52
53     // Listen for points
54     cepton_sdk::api::SensorImageFrameCallback callback;
55     cepton_sdk::api::check_error(callback.initialize());
56     callback.listen([](cepton_sdk::SensorHandle handle, std::size_t n_points,
57                     const cepton_sdk::SensorImagePoint* c_image_points) {
58         std::printf("Received %i points from sensor %lli\n", (int)n_points,
59                     (long long)handle);
60     });
61
62     CaptureReplay replay(capture_path);
63     replay.run();
64 }

```

10.6.6 Stray

Listing 11: samples/advanced/stray.cpp

```

1  /**
2   * Sample code for stray filter usage.
3   */
4  #include <vector>
5
6  #include <cepton_sdk_api.hpp>
7
8  int main(int argc, char **argv) {
9      std::string capture_path;
10     if (argc >= 2) capture_path = argv[1];
11
12     // Initialize
13     auto options = cepton_sdk::create_options();
14     cepton_sdk::api::check_error(
15         cepton_sdk::api::initialize(options, capture_path));
16
17     cepton_sdk::api::SensorImageFrameCallback callback;
18     cepton_sdk::api::check_error(callback.initialize());
19     cepton_sdk::util::StrayFilter filter;
20     callback.listen([&](cepton_sdk::SensorHandle handle, std::size_t n_points,
21         const cepton_sdk::SensorImagePoint *c_image_points) {
22         // Get sensor
23         cepton_sdk::SensorInformation sensor_info;
24         cepton_sdk::api::check_error(
25             cepton_sdk::get_sensor_information(handle, sensor_info));
26
27         // Copy points to buffer
28         std::vector<cepton_sdk::SensorImagePoint> image_points;
29         image_points.insert(image_points.begin(), c_image_points,
30             c_image_points + n_points);
31
32         // Filter stray
33         filter.init(sensor_info);
34         filter.run((int)n_points, image_points.data());
35     });
36
37     // Run
38     cepton_sdk::api::check_error(cepton_sdk::api::wait(5.0f));
39 }

```

10.6.7 Transform

Listing 12: samples/advanced/transform.cpp

```

1  /**
2   * Sample code for transforming 3d points.
3   */
4  #include "cepton_sdk_api.hpp"
5
6  int main() {
7      // Create transform
8      std::array<float, 3> translation = {0.0f, 0.0f, 1.0f};
9      std::array<float, 4> rotation = {1.0f, 0.0f, 0.0f, 0.0f};

```

(continues on next page)

(continued from previous page)

```
10  auto compiled_transform = cepton_sdk::util::CompiledTransform::create(  
11      translation.data(), rotation.data());  
12  
13  // Apply transform  
14  cepton_sdk::util::SensorPoint point = {};  
15  compiled_transform.apply(point.x, point.y, point.z);  
16  printf("Point: [%f, %f, %f]\n", point.x, point.y, point.z);  
17  }
```

INDEX

C

cepton_sdk::api::check_error (C++ *function*), 21
 cepton_sdk::api::default_on_error (C++ *function*), 21
 cepton_sdk::api::get_sensor_information_by_serial_number (C++ *function*), 22
 cepton_sdk::api::get_sensor_serial_number (C++ *function*), 22
 cepton_sdk::api::get_time (C++ *function*), 21
 cepton_sdk::api::has_sensor_by_serial_number (C++ *function*), 22
 cepton_sdk::api::initialize (C++ *function*), 21
 cepton_sdk::api::is_end (C++ *function*), 21
 cepton_sdk::api::is_live (C++ *function*), 21
 cepton_sdk::api::log_error (C++ *function*), 21
 cepton_sdk::api::NetworkPacketCallback (C++ *class*), 22
 cepton_sdk::api::NetworkPacketCallback::~~NetworkPacketCallback (C++ *function*), 22
 cepton_sdk::api::NetworkPacketCallback::deinitialize (C++ *function*), 22
 cepton_sdk::api::NetworkPacketCallback::initialize (C++ *function*), 22
 cepton_sdk::api::SensorErrorCallback (C++ *class*), 21
 cepton_sdk::api::SensorErrorCallback::global_on_callback (C++ *function*), 22
 cepton_sdk::api::SensorImageFrameCallback (C++ *class*), 22
 cepton_sdk::api::SensorImageFrameCallback::~~SensorImageFrameCallback (C++ *function*), 22
 cepton_sdk::api::SensorImageFrameCallback::deinitialize (C++ *function*), 22
 cepton_sdk::api::SensorImageFrameCallback::initialize (C++ *function*), 22
 cepton_sdk::api::SensorImageFrameCallback::is_initialized (C++ *function*), 22
 cepton_sdk::api::wait (C++ *function*), 21
 cepton_sdk::capture_replay::close (C++ *function*), 19
 cepton_sdk::capture_replay::get_enable_loop (C++ *function*), 19
 cepton_sdk::capture_replay::get_filename (C++ *function*), 19
 cepton_sdk::capture_replay::get_length (C++ *function*), 19
 cepton_sdk::capture_replay::get_position (C++ *function*), 19
 cepton_sdk::capture_replay::get_speed (C++ *function*), 19
 cepton_sdk::capture_replay::get_start_time (C++ *function*), 19
 cepton_sdk::capture_replay::is_end (C++ *function*), 19
 cepton_sdk::capture_replay::is_open (C++ *function*), 19
 cepton_sdk::capture_replay::is_running (C++ *function*), 20
 cepton_sdk::capture_replay::open (C++ *function*), 19
 cepton_sdk::capture_replay::pause (C++ *function*), 20
 cepton_sdk::capture_replay::resume (C++ *function*), 20
 cepton_sdk::capture_replay::resume_blocking (C++ *function*), 19
 cepton_sdk::capture_replay::resume_blocking_once (C++ *function*), 19
 cepton_sdk::capture_replay::seek (C++ *function*), 19
 cepton_sdk::capture_replay::set_enable_loop (C++ *function*), 19
 cepton_sdk::capture_replay::set_speed (C++ *function*), 19
 cepton_sdk::clear (C++ *function*), 17
 cepton_sdk::Control (C++ *type*), 7
 cepton_sdk::create_frame_options (C++ *function*), 8
 cepton_sdk::create_options (C++ *function*), 9
 cepton_sdk::deinitialize (C++ *function*), 9
 cepton_sdk::FpNetworkReceiveCallback

(C++ type), 17
 cepton_sdk::FpSensorErrorCallback (C++ type), 9
 cepton_sdk::FrameMode (C++ type), 8
 cepton_sdk::FrameOptions (C++ type), 8
 cepton_sdk::get_control_flags (C++ function), 9
 cepton_sdk::get_error (C++ function), 5
 cepton_sdk::get_error_code_name (C++ function), 5
 cepton_sdk::get_frame_length (C++ function), 9
 cepton_sdk::get_frame_mode (C++ function), 9
 cepton_sdk::get_n_sensors (C++ function), 13
 cepton_sdk::get_port (C++ function), 9
 cepton_sdk::get_sensor_handle_by_serial_number (C++ function), 13
 cepton_sdk::get_sensor_information (C++ function), 13
 cepton_sdk::get_sensor_information_by_index (C++ function), 13
 cepton_sdk::has_control_flag (C++ function), 9
 cepton_sdk::initialize (C++ function), 9
 cepton_sdk::is_error_code (C++ function), 5
 cepton_sdk::is_fault_code (C++ function), 5
 cepton_sdk::listen_image_frames (C++ function), 15
 cepton_sdk::listen_network_packets (C++ function), 17
 cepton_sdk::Options (C++ type), 9
 cepton_sdk::SensorError (C++ class), 3
 cepton_sdk::SensorError::~~SensorError (C++ function), 3
 cepton_sdk::SensorError::code (C++ function), 3
 cepton_sdk::SensorError::ignore (C++ function), 3
 cepton_sdk::SensorError::is_error (C++ function), 3
 cepton_sdk::SensorError::is_fault (C++ function), 4
 cepton_sdk::SensorError::msg (C++ function), 3
 cepton_sdk::SensorError::name (C++ function), 3
 cepton_sdk::SensorError::operator bool (C++ function), 3
 cepton_sdk::SensorError::operator SensorErrorCode (C++ function), 3
 cepton_sdk::SensorError::operator= (C++ function), 3
 cepton_sdk::SensorError::SensorError (C++ function), 3
 cepton_sdk::SensorError::used (C++ function), 3
 cepton_sdk::SensorErrorCode (C++ type), 4
 cepton_sdk::SensorHandle (C++ type), 11
 cepton_sdk::SensorImagePoint (C++ type), 15
 cepton_sdk::SensorInformation (C++ type), 11
 cepton_sdk::SensorModel (C++ type), 11
 cepton_sdk::set_control_flags (C++ function), 9
 cepton_sdk::set_frame_options (C++ function), 9
 cepton_sdk::set_port (C++ function), 9
 cepton_sdk::unlisten_image_frames (C++ function), 16
 cepton_sdk::unlisten_network_packets (C++ function), 17
 cepton_sdk::util::Callback (C++ class), 24
 cepton_sdk::util::Callback::clear (C++ function), 25
 cepton_sdk::util::Callback::emit (C++ function), 25
 cepton_sdk::util::Callback::global_on_callback (C++ function), 25
 cepton_sdk::util::Callback::listen (C++ function), 25
 cepton_sdk::util::Callback::operator () (C++ function), 25
 cepton_sdk::util::CompiledTransform (C++ class), 24
 cepton_sdk::util::CompiledTransform::apply (C++ function), 24
 cepton_sdk::util::CompiledTransform::create (C++ function), 24
 cepton_sdk::util::convert_image_point_to_point (C++ function), 23
 cepton_sdk::util::convert_sensor_image_point_to_point (C++ function), 24
 cepton_sdk::util::FrameAccumulator (C++ class), 26
 cepton_sdk::util::FrameAccumulator::add_points (C++ function), 26
 cepton_sdk::util::FrameAccumulator::callback (C++ member), 26
 cepton_sdk::util::FrameAccumulator::clear (C++ function), 26
 cepton_sdk::util::FrameAccumulator::FrameAccumulator (C++ function), 26
 cepton_sdk::util::FrameAccumulator::get_options (C++ function), 26
 cepton_sdk::util::FrameAccumulator::set_options (C++ function), 26
 cepton_sdk::util::FrameDetector (C++ class), 25

cepton_sdk::util::FrameDetector::add_point (C++ enum), 27
 (C++ function), 25 cepton_sdk::util::Organizer::OrganizerSettings
 cepton_sdk::util::FrameDetector::frame_found (C++ class), 28
 (C++ member), 25 cepton_sdk::util::Organizer::OrganizerSettings::hor
 cepton_sdk::util::FrameDetector::frame_idx (C++ member), 28
 (C++ member), 25 cepton_sdk::util::Organizer::OrganizerSettings::hor
 cepton_sdk::util::FrameDetector::frame_x (C++ member), 28
 (C++ member), 25 cepton_sdk::util::Organizer::OrganizerSettings::mo
 cepton_sdk::util::FrameDetector::FrameDetector (C++ member), 28
 (C++ function), 25 cepton_sdk::util::Organizer::OrganizerSettings::ver
 cepton_sdk::util::FrameDetector::get_options (C++ member), 28
 (C++ function), 25 cepton_sdk::util::Organizer::OrganizerSettings::ver
 cepton_sdk::util::FrameDetector::reset (C++ member), 28
 (C++ function), 25 cepton_sdk::util::Organizer::RECENT
 cepton_sdk::util::FrameDetector::set_options (C++ enumerator), 27
 (C++ function), 25 cepton_sdk::util::Organizer::settings
 cepton_sdk::util::get_timestamp_usec (C++ function), 28
 (C++ function), 23 cepton_sdk::util::SensorPoint (C++ class),
 cepton_sdk::util::OrganizedCloud (C++ 23
 class), 26 cepton_sdk::util::SensorPoint::distance
 cepton_sdk::util::OrganizedCloud::CellInfo (C++ member), 23
 (C++ class), 27 cepton_sdk::util::SensorPoint::flags
 cepton_sdk::util::OrganizedCloud::CellInfo::occ (C++ member), 23
 (C++ member), 27 cepton_sdk::util::SensorPoint::image_x
 cepton_sdk::util::OrganizedCloud::CellInfo::orig (C++ member), 23
 (C++ member), 27 cepton_sdk::util::SensorPoint::image_z
 cepton_sdk::util::OrganizedCloud::getIndex (C++ member), 23
 (C++ function), 26 cepton_sdk::util::SensorPoint::intensity
 cepton_sdk::util::OrganizedCloud::height (C++ member), 23
 (C++ member), 26 cepton_sdk::util::SensorPoint::reserved
 cepton_sdk::util::OrganizedCloud::info_cells (C++ member), 24
 (C++ member), 27 cepton_sdk::util::SensorPoint::return_type
 cepton_sdk::util::OrganizedCloud::n_returns (C++ member), 23
 (C++ member), 27 cepton_sdk::util::SensorPoint::saturated
 cepton_sdk::util::OrganizedCloud::points (C++ member), 24
 (C++ member), 27 cepton_sdk::util::SensorPoint::timestamp
 cepton_sdk::util::OrganizedCloud::timestamp_end (C++ member), 23
 (C++ member), 26 cepton_sdk::util::SensorPoint::valid
 cepton_sdk::util::OrganizedCloud::timestamp_start (C++ member), 23
 (C++ member), 26 cepton_sdk::util::SensorPoint::x (C++
 cepton_sdk::util::OrganizedCloud::width (C++ member), 24
 (C++ member), 26 cepton_sdk::util::SensorPoint::y (C++
 cepton_sdk::util::Organizer (C++ class), 27 member), 24
 cepton_sdk::util::Organizer::binSize (C++ function), 28 cepton_sdk::util::SensorPoint::z (C++
 cepton_sdk::util::Organizer::CENTER (C++ enumerator), 27 member), 24
 cepton_sdk::util::Organizer::mode (C++ cepton_sdk::util::SensorPoint::[anonymous]
 function), 28 (C++ member), 24
 cepton_sdk::util::Organizer::organize_points
 (C++ function), 27
 cepton_sdk::util::Organizer::Organizer
 (C++ function), 27
 cepton_sdk::util::Organizer::OrganizerMode